

# I. Magnetic Dipoles

## Magnetization




Figure 5-16 The orbiting electron has its magnetic moment  $\mathbf{m}$  in the direction opposite to its angular momentum  $\mathbf{L}$  because the current is opposite to the electron's velocity.




Figure 5-14 A magnetic dipole consists of a small circulating current loop. The magnetic moment is in the direction normal to the loop by the right-hand rule.

### Diamagnetism

$$I = \frac{e}{2\pi/\omega} = \frac{e\omega}{2\pi}, \quad \bar{m} = -I \pi R^2 \hat{i}_z = -\frac{e\omega}{2\pi} \pi R^2 \hat{i}_z = -\frac{e\omega R^2}{2} \hat{i}_z$$

$$\text{Angular Momentum } \bar{L} = m_e R \bar{r} \times \bar{v} = m_e R (\omega R) (\hat{i}_r \times \hat{i}_\phi) = m_e \omega R^2 \hat{i}_z = -\frac{2m_e}{e} \bar{m}$$

(  $\bar{r} \times \bar{v}$  )  
linear momentum

$L$  is quantized in units of  $\frac{h}{2\pi}$ ,  $h = 6.62 \times 10^{-34}$  joule-sec (Planck's constant)

$$|\bar{m}| = \frac{e|L|}{2m_e} = \frac{eh}{2\pi(2)m_e} = \frac{eh}{4\pi m_e} \approx 9.3 \times 10^{-24} \text{ amp-m}^2$$

Imagine all Bohr magnetons in sphere of radius  $R$  aligned. Net magnetic moment is

$$m = m_B \left( \frac{4}{3} \pi R^3 \rho \right)$$

Total mass of sphere

$$\frac{A_0}{M_0}$$

Avogadro's number


$$= 6.023 \times 10^{26} \text{ molecules per kilogram-mole}$$

molecular weight


Bohr magneton  $m_B$

(smallest unit of magnetic moment)

For iron:  $\rho = 7.86 \times 10^3 \text{ kg/m}^3$ ,  $M_0 = 56$



(a)



(b)

Figure 9.0.1 (a) Current  $i$  in loop of radius  $R$  gives dipole moment  $m$ . (b) Spherical material of radius  $R$  has dipole moment approximated as the sum of atomic dipole moments.

For a current loop

$$m = i \pi R^2 = m_B \frac{4}{3} \pi R^3 \rho \frac{A_0}{M_0} \Rightarrow i = m_B \frac{4}{3} R \rho \frac{A_0}{M_0}$$

$$\text{For } R = 10 \text{ cm} \Rightarrow i = 9.3 \times 10^{-24} \left( \frac{4}{3} \right) (1) 7.86 \times 10^3 \frac{(6.023 \times 10^{26})}{56}$$

$$= 1.05 \times 10^5 \text{ Amperes}$$

Thus, an ordinary piece of iron can have the same magnetic moment as a current loop of radius 10 cm of  $10^5$  Amperes current.

## B. Magnetic Dipole Field

$$\vec{H} = \frac{\mu_0 m}{4\pi r^3} [2\cos\theta \vec{r} + \sin\theta \vec{e}_\theta] \quad (\text{multiply top \& bottom by } \mu_0)$$

Electric Dipole Field

$$\vec{E} = \frac{P}{4\pi\epsilon_0 r^3} [2\cos\theta \vec{r} + \sin\theta \vec{e}_\theta]$$

Analogy

$$P \rightarrow \mu_0 m$$

$$\vec{P} = N \vec{p} \Rightarrow \vec{M} = N \vec{m}, \quad N = \# \text{ of magnetic dipoles / Volume}$$

\swarrow Polarization      \swarrow magnetization

## II. Maxwell's Equations with Magnetization

### EQS

$$\nabla \cdot (\epsilon_0 \vec{E}) = \rho_u - \nabla \cdot \vec{P}$$

$$\rho_p = -\nabla \cdot \vec{P} \quad (\text{polarization or paired charge density})$$

$$\vec{n} \cdot [\epsilon_0 (\vec{E}^a - \vec{E}^b)] = -\vec{n} \cdot [\vec{P}^a - \vec{P}^b] + \nabla_s u$$

$$\nabla_{sp} = -\vec{n} \cdot [\vec{P}^a - \vec{P}^b]$$

### MQS Equations

$$\vec{B} = \mu_0 (\vec{H} + \vec{M}) \quad \text{Magnetic flux density } \vec{B} \text{ has units of Teslas (1 Tesla} = 10,000 \text{ Gauss)}$$

$$\nabla \cdot \vec{B} = 0$$

$$\vec{n} \cdot [\vec{B}^a - \vec{B}^b] = 0$$

$$\nabla \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$$

$$\nabla \times \vec{H} = \vec{J}$$

$$v = \frac{d\lambda}{dt}, \quad \lambda = \int_S \vec{B} \cdot d\vec{a} \quad (\text{total flux})$$

## III. Magnetic Field Intensity $H_z$ of a Uniformly Magnetized Cylinder





Figure 9.3.1 (a) Cylinder of circular cross-section uniformly magnetized in the direction of its axis. (b) Axial distribution of scalar magnetic potential and (c) axial magnetic field intensity. For these distributions, the cylinder length is assumed to be equal to its diameter.

$$\nabla_{sm} = -\vec{n} \cdot \mu_0 (\vec{M}^a - \vec{M}^b) \Rightarrow \nabla_{sm}(z=d/2) = \mu_0 M_0$$

$$\nabla_{sm}(z=-d/2) = -\mu_0 M_0$$

$$\nabla \times \vec{H} = \vec{J} = 0 \Rightarrow \vec{H} = -\nabla \Psi$$

$$\nabla \cdot (\mu_0 \vec{H}) = -\mu_0 \nabla^2 \Psi = \rho_m = -\nabla \cdot (\mu_0 \vec{M})$$

$$\nabla^2 \Psi = -\rho_m / \mu_0 \Rightarrow \Psi(\vec{r}) = \int_{V'} \frac{\rho_m(\vec{r}') dV'}{4\pi\mu_0 |\vec{r} - \vec{r}'|}$$


$$\Psi(z) = \int_{r'=0}^R \frac{\nabla_{sm}(z=d/2) 2\pi r' dr'}{4\pi\mu_0 |\vec{r} - \vec{r}'|} + \int_{r'=0}^R \frac{\nabla_{sm}(z=-d/2) 2\pi r' dr'}{4\pi\mu_0 |\vec{r} - \vec{r}'|}$$

$$= \int_{r'=0}^R \frac{\mu_0 M_0 2\pi r' dr'}{4\pi\mu_0 [r'^2 + (z-d/2)^2]^{1/2}} - \int_{r'=0}^R \frac{\mu_0 M_0 2\pi r' dr'}{4\pi\mu_0 [r'^2 + (z+d/2)^2]^{1/2}}$$


$$\int \frac{r' dr'}{[r'^2 + (z \pm d/2)^2]^{1/2}} = [r'^2 + (z \pm d/2)^2]^{1/2}$$

$$\Psi(z) = \frac{M_0}{2} \left\{ [r'^2 + (z-d/2)^2]^{1/2} \Big|_{r'=0}^R - [r'^2 + (z+d/2)^2]^{1/2} \Big|_{r'=0}^R \right\}$$

$$= \frac{M_0}{2} \left\{ [R^2 + (z-d/2)^2]^{1/2} - |z-d/2| - [R^2 + (z+d/2)^2]^{1/2} + |z+d/2| \right\}$$



$$H_z = -\frac{\partial \Psi}{\partial z} = \begin{cases} -\frac{M_0}{2} \left\{ \frac{z-d/2}{[R^2 + (z-d/2)^2]^{1/2}} - \frac{(z+d/2)}{[R^2 + (z+d/2)^2]^{1/2}} \right\} & |z| > \frac{d}{2} \\ -\frac{M_0}{2} \left\{ \frac{z-d/2}{[R^2 + (z-d/2)^2]^{1/2}} - \frac{(z+d/2)}{[R^2 + (z+d/2)^2]^{1/2}} + z \right\} & -\frac{d}{2} < z < \frac{d}{2} \end{cases}$$



### III. Toroidal Coil

(5)




Figure 9.4.1 Toroidal coil with donut-shaped magnetizable core.



Figure 9.4.2 Surface  $S$  enclosed by contour  $C$  used with Ampère's integral law to determine  $H$  in the coil shown in Figure 9.4.1.

$$\oint_C \vec{H} \cdot d\vec{l} = H_\phi 2\pi r = N_1 i \Rightarrow H_\phi = \frac{N_1 i}{2\pi r} \approx \frac{N_1 i}{2\pi R}$$

$$\Phi \approx B \frac{\pi w^2}{4}$$

$$\lambda = N_2 \Phi = N_2 B \frac{\pi w^2}{4}$$




Figure 9.4.3 Demonstration in which the  $B - H$  curve is traced out in the sinusoidal steady state.


$$V_H = i_1 R_1 = R_1 \frac{H_\phi 2\pi R}{N_1} \quad V_H = \text{(Horizontal Voltage to oscilloscope)}$$

$$V_2 = \frac{d\lambda_2}{dt} = i_2 R_2 + V_V = V_V + R_2 C_2 \frac{dV_V}{dt}$$


$$\text{If } R_2 \gg \frac{1}{C_2 \omega} \Rightarrow \frac{d\lambda_2}{dt} \approx R_2 C_2 \frac{dV_V}{dt} \Rightarrow \lambda_2 = R_2 C_2 V_V \quad (V_V = \text{Vertical Voltage to oscilloscope})$$

$$= \frac{\pi w^2}{4} N_2 B$$


$$V_V = \frac{1}{R_2 C_2} \frac{\pi w^2}{4} N_2 B$$



**Figure 9.4.4** Typical magnetization curve without hysteresis. For typical ferromagnetic solids, the saturation flux density is in the range of 1–2 Tesla. For ferromagnetic domains suspended in a liquid, it is .02–.04 Tesla.



**Figure 9.4.6** Magnetization characteristic for material showing hysteresis with typical values of  $B_r$  and  $H_c$  given in Table 9.4.2. The curve is obtained after many cycles of sinusoidal excitation in apparatus such as that of Figure 9.4.3. The trajectory is traced out in response to a sinusoidal current, as shown by the inset.



**Figure 9.4.5** Polycrystalline ferromagnetic material viewed at the domain level. In the absence of an applied magnetic field, the domain moments tend to cancel. (This presumes that the material has not been left in a magnetized state by a previously applied field.) As a field is applied, the domain walls shift, giving rise to a net magnetization. In ideal materials, saturation results as all of the domains combine into one. In materials used for bulk fabrication of transformers, imperfections prevent the realization of this state.

Massachusetts Institute of Technology  
 Department of Electrical Engineering and Computer Science  
 6.641 Electromagnetic Fields, Forces, and Motion  
 Spring 2003

Lecture Notes 7, 3/4/03 (Supplement)

# I. Magnetic Circuits




Figure 6-8 The magnetic field is zero within an infinitely permeable magnetic core and is constant in the air gap if we neglect fringing. The flux through the air gap is constant at every cross section of the magnetic circuit and links the  $N$  turn coil  $N$  times.

In iron core:

$$\lim_{\mu \rightarrow \infty} \vec{B} = \mu \vec{H} \Rightarrow \begin{cases} \vec{H} = 0 \\ \vec{B} \text{ finite} \end{cases}$$

$$\oint \vec{H} \cdot d\vec{\ell} = Hs = Ni \Rightarrow H = \frac{Ni}{s}$$

$$\Phi = \mu_0 H D d = \frac{\mu_0 D d N i}{s}$$

$$\oint \vec{B} \cdot d\vec{a} = 0$$

$$\lambda = N\Phi = \frac{\mu_0 D d}{s} N^2 i \Rightarrow L = \frac{\lambda}{i} = \frac{\mu_0 D d}{s} N^2$$

## II. Reluctance

$$\mathcal{R} = \frac{Ni}{\Phi} = \frac{s}{\mu_0 D d} = \frac{(\text{length})}{(\text{permeability})(\text{cross-sectional area})}$$

[Reluctance, analogous to resistance]




Figure 6-11 Magnetic circuits are most easily analyzed from a circuit approach where (a) reluctances in series add and (b) permeances in parallel add.

### A. Reluctances In Series

$$\mathcal{R}_1 = \frac{s_1}{\mu_1 a_1 D}, \quad \mathcal{R}_2 = \frac{s_2}{\mu_2 a_2 D}$$

$$\Phi = \frac{Ni}{\mathcal{R}_1 + \mathcal{R}_2}$$



$$\oint_C \vec{H} \cdot d\vec{\ell} = H_1 S_1 + H_2 S_2 = N i$$

$$\Phi = \mu_1 H_1 a_1 D = \mu_2 H_2 a_2 D$$

$$H_1 = \frac{\mu_2 a_2 N i}{\mu_1 a_1 S_2 + \mu_2 a_2 S_1} ; H_2 = \frac{\mu_1 a_1 N i}{\mu_1 a_1 S_2 + \mu_2 a_2 S_1}$$

### B. Reluctances in Parallel


$$\oint_C \vec{H} \cdot d\vec{\ell} = H_1 s = H_2 s = N i \Rightarrow H_1 = H_2 = \frac{N i}{s}$$

$$\Phi = (\mu_1 H_1 a_1 + \mu_2 H_2 a_2) D = \frac{N i (\mu_1 a_1 + \mu_2 a_2) D}{\mu_1 a_1 S_1 + \mu_2 a_2 S_2} = N i \left( \frac{\mu_1 a_1 + \mu_2 a_2}{\mu_1 a_1 S_1 + \mu_2 a_2 S_2} \right)$$

$$P_1 = \frac{1}{R_1} ; P_2 = \frac{1}{R_2}$$

$$P = \frac{1}{R} \quad [\text{Permeance, analogous to Conductance}]$$

### III. Transformers (Ideal)



$$\left. \begin{aligned} \frac{v_1}{v_2} &= \frac{N_1}{N_2} \\ \frac{i_1}{i_2} &= \frac{N_2}{N_1} \end{aligned} \right\} = v_1 i_1 = v_2 i_2$$

(a)

Figure 6-13 (a) An ideal transformer relates primary and secondary voltages by the ratio of turns while the currents are in the inverse ratio so that the input power equals the output power. The H field is zero within the infinitely permeable core. (b) In a real transformer the nonlinear B-H hysteresis loop causes a nonlinear primary current  $i_1$  with an open circuited secondary ( $i_2 = 0$ ) even though the imposed sinusoidal voltage  $v_1 = V_0 \cos \omega t$  fixes the flux to be sinusoidal. (c) A more complete transformer equivalent circuit.

④

## A. Voltage/Current Relationships

$$\Phi = \frac{N_1 i_1 - N_2 i_2}{R} ; R = \frac{l}{\mu A}$$

Another way:  $\oint_C \vec{H} \cdot d\vec{l} = Hl = N_1 i_1 - N_2 i_2$

$$H = \frac{N_1 i_1 - N_2 i_2}{l}$$

$$\Phi = \mu H A = \frac{\mu A}{l} (N_1 i_1 - N_2 i_2) = \frac{(N_1 i_1 - N_2 i_2)}{R}$$

$$\lambda_1 = N_1 \Phi = \frac{\mu A}{l} (N_1^2 i_1 - N_1 N_2 i_2) = L_1 i_1 - M i_2$$

$$\lambda_2 = N_2 \Phi = \frac{\mu A}{l} (N_1 N_2 i_1 - N_2^2 i_2) = -M i_1 + L_2 i_2$$

$$L_1 = N_1^2 L_0, L_2 = N_2^2 L_0, M = N_1 N_2 L_0, L_0 = \frac{\mu A}{l} = 1/R$$

$$M = [L_1 L_2]^{1/2}$$

$$v_1 = \frac{d\lambda_1}{dt} = L_1 \frac{di_1}{dt} - M \frac{di_2}{dt} = N_1 L_0 \left[ N_1 \frac{di_1}{dt} - N_2 \frac{di_2}{dt} \right]$$

$$v_2 = \frac{d\lambda_2}{dt} = +M \frac{di_1}{dt} - L_2 \frac{di_2}{dt} = N_2 L_0 \left[ +N_1 \frac{di_1}{dt} - N_2 \frac{di_2}{dt} \right]$$

$$\frac{v_1}{v_2} = \frac{N_1}{N_2}$$

$$\lim_{\mu \rightarrow \infty} H \rightarrow 0 \Rightarrow N_1 i_1 = N_2 i_2 \Rightarrow \frac{i_1}{i_2} = \frac{N_2}{N_1}$$

$$\frac{v_1 i_1}{v_2 i_2} = 1$$




Figure 9.7.6 Circuit representation of a transformer as defined by the terminal relations of (12) or of an ideal transformer as defined by (13).

### B. Impedance Transformer

$$v_2 = i_2 R_L$$

$$R_{\text{primary}} = \frac{v_1}{i_1} = \frac{N_1}{N_2} \frac{v_2}{\frac{i_2 N_2}{N_1}} = \left(\frac{N_1}{N_2}\right)^2 \frac{v_2}{i_2} = R_L \left(\frac{N_1}{N_2}\right)^2$$

C. When are the ideal transformer relations approximately correct?




Figure 9.7.8 Transformer with a load resistance  $R$  that includes the internal resistance of the secondary winding.

$$\frac{d\lambda_2}{dt} = +i_2 R = M \frac{di_1}{dt} - L_2 \frac{di_2}{dt}$$

$$i_1 = I(t) = \text{Re}[\hat{I} e^{j\omega t}]$$

$$i_2 = \text{Re}[\hat{i}_2 e^{j\omega t}]$$

$$L_2 \frac{di_2}{dt} + i_2 R = M \frac{di_1}{dt} \Rightarrow \hat{i}_2 [L_2 j\omega + R] = M j\omega \hat{I}$$

$$\frac{\hat{i}_2}{\hat{I}} = \frac{M j\omega}{L_2 j\omega + R} \approx \frac{M}{L_2} = \frac{N_1 N_2 L_0}{N_2^2 L_0} = \frac{N_1}{N_2}$$

if  $L_2 j\omega \gg R$